



EUROPEAN
SPALLATION
SOURCE

Description	Engineering Manual
Document number	ESS-XXXXXXX
Date	September 12, 2017
Revision	0.1
State	Early Draft
Classification	Public
Page	1 (16)

ICS Engineering Manual

FOR AN INVENTORY SYSTEM WITH JIRA AND EPICS

	Name (Role/Title)
Author	Jeong Han Lee (han.lee@esss.se)
Reviewer	TBD
Owner	ICS
Approver	ICS

Contents

Contents	2
1 Overview	3
1.1 Inventory Workflow	4
1.2 Components	8
1.3 Troubleshooting	8
2 Honeywell Xenon Scanners 1900 and 1902g	9
2.1 Basic Configuration	9
3 Predefined Bar Codes	10
3.1 Vendor Codes	10
3.2 FormFactor Codes	12
3.3 Model Codes	13
4 Action Bar Codes	15
5 Outlook	16

Description	Engineering Manual
Document number	ESS-XXXXXXX
Date	September 12, 2017
Revision	0.1
State	Early Draft
Classification	Public

1 Overview

There are infinite ways to develop and maintain an inventory system. However, this inventory is the unique and **temporary** solution for the ICS Lab, especially, where the author works at. This inventory system is designed to minimize our time when we register an item to the existent JIRA ICS HW&I group inventory task. Therefore, it does **NOT** provide any fancy and beautiful ways to interact with users, BUT provide the minimal tool to monitor and track any equipment in ICS, ESS, and any IK partner. And the system only provide the following features :

- Do stock an item to JIRA, and do Add-and-Print its barcodes.
- Do stock an item to JIRA, and do Add-and-Print its barcodes.
- Delete an item from JIRA.
- Print the existent (created) label (in case, the printer doesn't work properly)



Figure 1 CS-Studio User Interface Screen Examples.

Description	Engineering Manual
Document number	ESS-XXXXXXX
Date	September 12, 2017
Revision	0.1
State	Early Draft
Classification	Public

1.1 Inventory Workflow

1.1.1 How to stock an item at the first time to JIRA

The mandatory steps are defined the following procedures :

Scan the Serial Number on the equipment with the Xenon 190x barcode scanner.




Figure 2 User Interface Screen Example after the serial number scan.

Scan one of 3.3 Model Codes in the manual with the Xenon 190x scanner.




Figure 3 User Interface Screen Example after the Model Name scan.

Description	Engineering Manual
Document number	ESS-XXXXXXXX
Date	September 12, 2017
Revision	0.1
State	Early Draft
Classification	Public

Both case in below, the created labels are attached in the JIRA issue.

1. Scan Enable Label Printing after JIRA action if one wants to print labels (Default)
2. Scan Disable Label Printing after JIRA action if one wants not print labels




Figure 4 User Interface Screen Example for Enable and Disable Labels

Scan Create an JIRA issue in the manual




Figure 5 User Interface Screen Example after the Create an JIRA scan.

Description	Engineering Manual
Document number	ESS-XXXXXXX
Date	September 12, 2017
Revision	0.1
State	Early Draft
Classification	Public

Attach two barcodes in the reserved box, an equipment, or both.



Figure 6 Equipment with labels. The small one should be trimmed properly.

1.1.2 How to add and print barcodes for an Item which has registered in JIRA

1. Define the TAG number which one wants to delete it via CS-Studio User Interface or caput
caput ICSLAB:IssueNumber TAG-XXX
2. Scan the Serial Number on the equipment with the Xenon 190x barcode scanner.
3. Scan Model Name in the manual with the Xenon 190x scanner.
4. Both case in below, the updated labels are attached in the JIRA issue.
 - a) Scan Enable Label Printing after JIRA action if one wants to print the updated label (Default)
 - b) Scan Disable Label Printing after JIRA action if one wants not print the updated label
5. Scan Update an JIRA issue in the engineering manual

1.1.3 How to delete the existent Item

1. Define the TAG number which one wants to delete it via CS-Studio User Interface or caput
caput ICSLAB:IssueNumber TAG-XXX
2. Scan Delete an JIRA issue Barcode in the manual with the Xenon 190x barcode scanner.

Description	Engineering Manual
Document number	ESS-XXXXXXX
Date	September 12, 2017
Revision	0.1
State	Early Draft
Classification	Public

1.1.4 Print the existent labels

In case, there is the printer issue, for example, print only one of two labels, not responding, and so on.

1. Please check the printer status at <http://localhost:631/> and resolve it. Note that one should know the basic CUPS configuration.
2. Print the existent label by scanning the barcode (Print the last existent label) in the manual. Note that this action will print only the recent created labels.




Figure 7 Bar code in the manual for the Print the Existent Label.

Description	Engineering Manual
Document number	ESS-XXXXXXX
Date	September 12, 2017
Revision	0.1
State	Early Draft
Classification	Public

1.2 Components

1.2.1 Hardware

- Honeywell Xenon 1900g (Wire) or 1902g (Wireless) Barcode scanner
- DYMO LabelWriter 450 Duo

1.2.2 Software

- Linux OS (tested with Debian 8)
- EPICS IOC <https://github.com/jeonghanlee/hw-xenon1900>
- JIRA <https://jira.esss.lu.se/projects/TAG/summary>
- DYMO LabelWriter 450 Duo CUP Driver
<http://www.dymo.com/en-US/dymo-label-sdk-and-cups-drivers-for-linux-dymo-label-sdk-cups-linux-p--1>

1.3 Troubleshooting

Description	Engineering Manual
Document number	ESS-XXXXXXX
Date	September 12, 2017
Revision	0.1
State	Early Draft
Classification	Public

2 Honeywell Xenon Scanners 1900 and 1902g

Note that there are different procedure to setup Xenon 1900 corded scanner and Xenon 1902g cordless scanner. Please consult each manual in detail.

2.1 Basic Configuration



Figure 8 Default Settings.



Figure 9 USB Serial Setting.



Figure 10 Silent Mode for Corded Scanner.



Figure 11 Silent Mode for Cordless Scanner.

Description	Engineering Manual
Document number	ESS-XXXXXXXX
Date	September 12, 2017
Revision	0.1
State	Early Draft
Classification	Public

3 Predefined Bar Codes

3.1 Vendor Codes



undefined



ess



mrf



ioxos



moxa



nat



concurrent



schroff

Description	Engineering Manual
Document number	ESS-XXXXXXXX
Date	September 12, 2017
Revision	0.1
State	Early Draft
Classification	Public



struck



caen



raritan




dymo




Honeywell

Description	Engineering Manual
Document number	ESS-XXXXXXXX
Date	September 12, 2017
Revision	0.1
State	Early Draft
Classification	Public

3.2 FormFactor Codes



undefined



MTCA



PCIE











VME



FMC

Description	Engineering Manual
Document number	ESS-XXXXXXXX
Date	September 12, 2017
Revision	0.1
State	Early Draft
Classification	Public

3.3 Model Codes

	undefined
	PCIE EVR 300DC
	MTCA EVR 300U
	Concurrent CPU
	MTCA 3U Crate
	NAT Power Module
	NAT MCH PHYS
	Barcode Scanner Xenon 190x

Description	Engineering Manual
Document number	ESS-XXXXXXXX
Date	September 12, 2017
Revision	0.1
State	Early Draft
Classification	Public



Dymo LabelWriter 450 Duo



IOxOS ADC 3110 A0



IOxOS ADC 3117



IOxOS IFC1410



IOxOS IFC1420



MRF VME-EVG-230



MRF VME-FOUT-12

Description	Engineering Manual
Document number	ESS-XXXXXXX
Date	September 12, 2017
Revision	0.1
State	Early Draft
Classification	Public

4 Action Bar Codes



Clear all scanned PVs



————— place holder —————



Enable Label Printing after JIRA action



Disable Label Printing after JIRA action



Print the last existent label



————— place holder —————



Create an JIRA issue



Update an JIRA issue (Define the issue number first)

Description	Engineering Manual
Document number	ESS-XXXXXXX
Date	September 12, 2017
Revision	0.1
State	Early Draft
Classification	Public



Delete an JIRA issue (Define the issue number first)

5 Outlook

The system has the limited functionality for the usage of ICS Tuna Lab, since I would like to save at least 5 mins while stocking an equipment into the existent JIRA project. With the current implementation, it actually save my time a lot, so I can work more valuable subjects than tedious and time-consuming open-read-write-print activities when I have 50 boxes of an equipment. This system fulfilled already what I would like to achieve, i.e., saving 5 mins per an equipment. Therefore, I ended this development.

However, it may be the good starting point if one want to implement this system with any relational database, which is more flexible than the restricted JIRA project, which I don't have any permission to modify their structure. Please contact me through han.lee@esss.se if one has any comments on this system.